



Installation Guide

SUSE Manager 4.1

February 19, 2021



Table of Contents

Installation Guide Overview	1
General Requirements	2
Obtain Your SUSE Customer Center Credentials	2
Obtain the Unified Installer	3
Supported Browsers for the SUSE Manager Web UI	3
SSL Certificates	3
Hardware Requirements	3
Network Requirements	7
Supported Client Systems	15
Public Cloud Requirements	16
Installation	19
Installing SUSE Manager 4.1 Server	19
SUSE Manager 4.1 Proxy	23
Install SUSE Manager in a Virtual Machine Environment with JeOS	25
Install SUSE Manager Proxy from packages	28
Installing on IBM Z	30
Setting Up	34
SUSE Manager Server Setup	34
SUSE Manager Proxy Registration	40
SUSE Manager Proxy Setup	44
Web Interface Setup	49
Public Cloud Setup	52
Setup Wizard	55
GNU Free Documentation License	57

Installation Guide Overview

Publication Date: 2021-02-19

This book provides guidance on installing SUSE Manager. It is split into three sections:

- Requirements: Describes the hardware, software, and networking requirements that you require before you begin.
- Installation: Describes the process to install SUSE Manager components.
- Setting Up: Describes the initial steps you need to take after installation to make your SUSE Manager environment ready to use.

General Requirements

Before you begin installation, ensure that you have:

- Current SUSE Customer Center organization credentials
- Access to installation media
- Environment meets the hardware and networking requirements
- Any required SSL certificates for your environment

This section contains more information on each of these requirements.

For a complete list of supported clients and features, see [[Client-configuration](#) › [Supported-features](#) ›].



SUSE Manager 4.1 is based on SLES 15 SP2 as the host operating system. SUSE Manager comes with a maintenance lifecycle of two years. For more information, see <https://www.suse.com/lifecycle/>.

Long Term Service Pack Support (LTSS) for 15 cannot be added to SUSE Manager. It is also not possible to use SLES for SAP as a base for SUSE Manager to increase the lifecycle of the underlying operating system.

Obtain Your SUSE Customer Center Credentials

Create an account with SUSE Customer Center before installation of SUSE Linux Enterprise Server and SUSE Manager.

Procedure: Obtaining Your SCC Organization Credentials

1. Navigate to <https://scc.suse.com/login> in your Web browser.
2. Log in to your SCC account, or follow the prompts to create a new account.
3. If you have not yet done so, click **[Connect to an Organization]** and type or search for your organization.
4. Click **[Manage my Organizations]** and select your organization from the list by clicking on the organization name.
5. Click the **[Organization]** tab, and then select the **[Organization Credentials]** tab.
6. Record your login information for use during SUSE Manager setup.

Depending on your organization's setup, you might also need to activate your subscription, using the **[Activate Subscriptions]** menu.

Obtain the Unified Installer

SUSE Manager Server and Proxy can be installed with the SUSE Linux Enterprise Unified Installer.

You only require a valid registration code for SUSE Manager. You do not require a separate code for SLES 15 SP2.

If not already done, download the SUSE Linux Enterprise Unified Installer from <https://download.suse.com/index.jsp>. Direct link to SUSE Linux Enterprise 15 SP2, required to install SUSE Manager 4.1: https://download.suse.com/index.jsp?product_id=&search=Search&families=22609&version=68287. For a later version or a different architecture, such as IBM Z, select the respective item. With the Unified Installer you can install many SLE-based base products such as SLES, SLES for SAP Applications, or SUSE Manager.

Supported Browsers for the SUSE Manager Web UI

In order to use the Web UI to manage your SUSE Manager environment, you will need to ensure you are running an up to date web browser.

SUSE Manager is supported on:

- Latest Firefox browser shipped with SUSE Linux Enterprise Server
- Latest Chrome browser on all operating systems
- Latest Edge browser shipped with Windows

Windows Internet Explorer is not supported. The SUSE Manager Web UI will not render correctly under Windows Internet Explorer.

SSL Certificates

SUSE Manager uses SSL certificates to ensure that clients are registered to the correct server. By default, SUSE Manager uses a self-signed certificate. If you have certificates signed by a third-party CA, you can import them to your SUSE Manager installation.

- For more on self-signed certificates, see [[Administration › Ssl-certs-selfsigned ›](#)].
- For more on imported certificates, see [[Administration › Ssl-certs-imported ›](#)].

Hardware Requirements

This table outlines hardware and software requirements for the SUSE Manager Server and Proxy, on x86_64 and IBM Power PC architecture.

For IBM Z hardware requirements, see [[Installation › Install-ibmz ›](#)].

For SUSE Manager for Retail hardware requirements, see [[Retail > Retail-requirements >](#)].

Server Hardware Requirements

SUSE Manager Server stores packages in the `/var/spacewalk/` directory. Repository synchronization fails if this directory runs out of disk space. You can estimate how much space the `/var/spacewalk/` directory requires based on the clients and repositories you plan to mirror.

Table 1. Server Hardware Requirements for x86_64 Architecture

Hardware	Details	Recommendation
CPU	-	Minimum 4 dedicated 64-bit CPU cores
RAM	Test Server	Minimum 8 GB
	Base Installation	Minimum 16 GB
	Production Server	Minimum 32 GB
Disk Space	<code>/</code> (root directory)	Minimum 24 GB
	<code>/var/lib/pgsql</code>	Minimum 50 GB
	<code>/var/spacewalk</code>	Minimum 50 GB per SUSE product and 360 GB per Red Hat product
	<code>/var/cache</code>	Minimum 10 GB. Add 100 MB per SUSE product, 1 GB per Red Hat or other product. Double the space if the server is an ISS Master.
	Swap space	3 GB

For more information about inter-server synchronization (ISS), see [[Administration > Iss >](#)].

Table 2. Server Hardware Requirements for IBM POWER8 or POWER9 Architecture

Hardware	Details	Recommendation
CPU		Minimum 4 dedicated cores
RAM	Test Server	Minimum 8 GB
	Base Installation	Minimum 16 GB

Hardware	Details	Recommendation
	Production Server	Minimum 32 GB
Disk Space	/ (root directory)	Minimum 100 GB
	/var/lib/pgsql	Minimum 50 GB
	/var/pacewalk	Minimum 50 GB per SUSE product and 360 GB per Red Hat product
	/var/cache	Minimum 10 GB. Add 100 MB per SUSE product, 1 GB per Red Hat or other product. Double the space if the server is an ISS Master.
	Swap space	3 GB

For more information about inter-server synchronization (ISS), see [[Administration](#) > [Iss](#) >].

Proxy Hardware Requirements

Table 3. Proxy Hardware Requirements

Hardware	Details	Recommendation
CPU		Minimum 2 dedicated 64-bit CPU cores
RAM	Test Server	Minimum 2 GB
	Production Server	Minimum 8 GB
Disk Space	/ (root directory)	Minimum 24 GB
	/srv	Minimum 100 GB
	/var/cache (Squid)	Minimum 100 GB

SUSE Manager Proxy caches packages in the `/var/cache/` directory. If there is not enough space available in `/var/cache/`, the proxy will remove old, unused packages and replace them with newer packages.

As a result of this behavior:

- The larger `/var/cache/` directory is on the proxy, the less traffic there will be between it and the SUSE Manager Server.

- By making the `/var/cache/` directory on the proxy the same size as `/var/spacewalk/` on the SUSE Manager Server, you avoid a large amount of traffic after the first synchronization.
- The `/var/cache/` directory can be small on the SUSE Manager Server compared to the proxy. For a guide to size estimation, see the [Server Hardware Requirements](#) section.

Storage Devices and Permissions

We recommend that the repositories and the database for SUSE Manager are stored on separate storage devices. This will help to avoid data loss. You must set up the storage devices before you run the YaST SUSE Manager setup procedure.

SUSE Manager requires three different volumes:

- Database volume: `/var/lib/pgsql`
- Channel volume: `/var/lib/spacewalk`
- Cache: `/var/cache`

We recommend you use XFS as the filesystem type for all volumes. Additionally, for on-premise installations, consider using logical volume management (LVM) to manage the disks. The size of the disk for repositories storage is dependent on the number of distributions and channels you intend to manage with SUSE Manager. See the tables in this section for guides to estimate the size required.

On your SUSE Manager Server, use this command to find all available storage devices:

```
hwinfo --disk | grep -E "Device File:"
```

Use the `lsblk` command to see the name and size of each device.

Use the `suma-storage` command with the device names to set up the external disks as the locations for the database and repositories:

```
suma-storage <channel_devicename> [<database_devicename>]
```

The external storage volumes are set up as XFS partitions mounted at `/manager_storage` and `/pgsql_storage`.

It is possible to use the same storage device for both channel data and the database. This is not recommended, as growing channel repositories might fill up the storage, which poses a risk to database integrity. Using separate storage devices may also increase performance. If you want to use a single storage device, run `suma-storage` with a single device name parameter.

If you are installing a proxy, the `suma-storage` command only takes a single device name

parameter and will set up the external storage location as the Squid cache.

When you create disk partitions for the SUSE Manager Server and Proxy, ensure you set the permissions correctly.

For `/var/lib/pgsql`:

- Owner: Read, Write, Execute
- Group: Read, Execute
- User: None

For `/var/pacewalk`:

- Owner: Read, Write, Execute
- Group: Read, Write, Execute
- User: Read, Execute

Check the permissions with this command:

```
ls -l /var/lib/pgsql /var/pacewalk
```

The output should look like this:

```
drwxr-x--- 1 postgres postgres /var/lib/pgsql
drwxrwxr-x 1 wwwrun  www    /var/pacewalk
```

If required, change the permissions with these commands:

```
chmod 750 /var/lib/pgsql
chmod 775 /var/pacewalk
```

And owners with:

```
chown postgres:postgres /var/lib/pgsql
chown wwwrun:www /var/pacewalk
```

Network Requirements

This section details the networking and port requirements for SUSE Manager.

Fully Qualified Domain Name (FQDN)

The SUSE Manager server must resolve its FQDN correctly. If the FQDN cannot be resolved, it can cause serious problems in a number of different components.

For more information about configuring the hostname and DNS, see <https://documentation.suse.com/sles/15-SP2/html/SLES-all/cha-network.html#sec-network-yast-change-host>.

Hostname and IP Address

To ensure that the SUSE Manager domain name can be resolved by its clients, both server and client machines must be connected to a working DNS server. You also need to ensure that reverse lookups are correctly configured.

For more information about setting up a DNS server, see <https://documentation.suse.com/sles/15-SP2/html/SLES-all/cha-dns.html>.

Using a Proxy When Installing from SUSE Linux Enterprise Media

If you are on an internal network and do not have access to SUSE Customer Center, you can set up and use a proxy during installation.

For more information about configuring a proxy for access to SUSE Customer Center during a SUSE Linux Enterprise installation, see <https://documentation.suse.com/sles/15-SP2/html/SLES-all/cha-boot-parameters.html#sec-boot-parameters-advanced-proxy>.



The hostname of SUSE Manager must not contain uppercase letters as this may cause jabberd to fail. Choose the hostname of your SUSE Manager server carefully. Although changing the server name is possible and supported, it is important to plan for this change before going ahead with it. When you change the hostname of the server, all clients attached to the server must be made aware of the change.

In a production environment, the SUSE Manager Server and clients should always use a firewall. For a comprehensive list of the required ports, see [[Installation > Ports >](#)].


For more information on disconnected setup and port configuration, see [administration:disconnected-setup.pdf](#).

Network Ports

This section contains a comprehensive list of ports that are used for various communications within SUSE Manager.

You will not need to open all of these ports. Some ports only need to be opened if you are using the service that requires them.

This image shows the main ports used in SUSE Manager:



External Inbound Server Ports

External inbound ports must be opened to configure a firewall on the SUSE Manager Server to protect the server from unauthorized access.

Opening these ports allows external network traffic to access the SUSE Manager Server.

Table 4. External Port Requirements for SUSE Manager Server

Port number	Protocol	Used By	Notes
22			Required for ssh-push and ssh-push-tunnel contact methods.
67	TCP/UDP	DHCP	Required only if clients are requesting IP addresses from the server.

Port number	Protocol	Used By	Notes
69	TCP/UDP	TFTP	Required if server is used as a PXE server for automated client installation.
80	TCP	HTTP	Required temporarily for some bootstrap repositories and automated installations. Port 80 is not used to serve the Web UI.
443	TCP	HTTPS	Web UI, client, and proxy requests.
4505	TCP	salt	Required to accept communication requests from clients. The client initiates the connection, and it stays open to receive commands from the Salt master.
4506	TCP	salt	Required to accept communication requests from clients. The client initiates the connection, and it stays open to report results back to the Salt master.
5222	TCP	osad	Required to push OSAD actions to clients.
5269	TCP	jabberd	Required to push actions to and from a proxy.
25151	TCP	Cobbler	

External Outbound Server Ports

External outbound ports must be opened to configure a firewall on the SUSE Manager Server to

restrict what the server can access.

Opening these ports allows network traffic from the SUSE Manager Server to communicate with external services.

Table 5. External Port Requirements for SUSE Manager Server

Port number	Protocol	Used By	Notes
80	TCP	HTTP	Required for SUSE Customer Center. Port 80 is not used to serve the Web UI.
443	TCP	HTTPS	Required for SUSE Customer Center.
5269	TCP	jabberd	Required to push actions to and from a proxy.
25151	TCP	Cobbler	

Internal Server Ports

Internal ports are used internally by the SUSE Manager Server. Internal ports are only accessible from `localhost`.

In most cases, you will not need to adjust these ports.

Table 6. Internal Port Requirements for SUSE Manager Server

Port number	Notes
2828	Satellite-search API, used by the RHN application in Tomcat and Taskomatic.
2829	Taskomatic API, used by the RHN application in Tomcat.
8005	Tomcat shutdown port.
8009	Tomcat to Apache HTTPD (AJP).
8080	Tomcat to Apache HTTPD (HTTP).
9080	Salt-API, used by the RHN application in Tomcat and Taskomatic.

Port number	Notes
32000	Port for a TCP connection to the Java Virtual Machine (JVM) that runs Taskomatic and satellite-search.

Port 32768 and higher are used as ephemeral ports. These are most often used to receive TCP connections. When a TCP connection request is received, the sender will choose one of these ephemeral port numbers to match the destination port. You can use this command to find out which ports are ephemeral ports:

```
cat /proc/sys/net/ipv4/ip_local_port_range
```

External Inbound Proxy Ports

External inbound ports must be opened to configure a firewall on the SUSE Manager Proxy to protect the proxy from unauthorized access.

Opening these ports allows external network traffic to access the SUSE Manager proxy.

Table 7. External Port Requirements for SUSE Manager Proxy

Port number	Protocol	Used By	Notes
22			Required for ssh-push and ssh-push-tunnel contact methods. Clients connected to the proxy initiate check in on the server and hop through to clients.
67	TCP/UDP	DHCP	Required only if clients are requesting IP addresses from the server.
69	TCP/UDP	TFTP	Required if the server is used as a PXE server for automated client installation.
443	TCP	HTTPS	Web UI, client, and proxy requests.

Port number	Protocol	Used By	Notes
4505	TCP	salt	Required to accept communication requests from clients. The client initiates the connection, and it stays open to receive commands from the Salt master.
4506	TCP	salt	Required to accept communication requests from clients. The client initiates the connection, and it stays open to report results back to the Salt master.
5222	TCP		Required to push OSAD actions to clients.
5269	TCP		Required to push actions to and from the server.

External Outbound Proxy Ports

External outbound ports must be opened to configure a firewall on the SUSE Manager Proxy to restrict what the proxy can access.

Opening these ports allows network traffic from the SUSE Manager Proxy to communicate with external services.

Table 8. External Port Requirements for SUSE Manager Proxy

Port number	Protocol	Used By	Notes
80			Used to reach the server.
443	TCP	HTTPS	Required for SUSE Customer Center.
5269	TCP		Required to push actions to and from the server.

External Client Ports

External client ports must be opened to configure a firewall between the SUSE Manager Server and its clients.

In most cases, you will not need to adjust these ports.

Table 9. External Port Requirements for SUSE Manager Clients

Port number	Direction	Protocol	Notes
22	Inbound	SSH	Required for ssh-push and ssh-push-tunnel contact methods.
80	Outbound		Used to reach the server or proxy.
5222	Outbound	TCP	Required to push OSAD actions to the server or proxy.
9090	Outbound	TCP	Required for Prometheus user interface.
9093	Outbound	TCP	Required for Prometheus alert manager.
9100	Outbound	TCP	Required for Prometheus node exporter.
9117	Outbound	TCP	Required for Prometheus Apache exporter.
9187	Outbound	TCP	Required for Prometheus PostgreSQL.

Required URLs

There are some URLs that SUSE Manager must be able to access to register clients and perform updates. In most cases, allowing access to these URLs is sufficient:

- scc.suse.com

- updates.suse.com

If you are using non-SUSE clients you might also need to allow access to other servers that provide specific packages for those operating systems. For example, if you have Ubuntu clients, you will need to be able to access the Ubuntu server.

For more information about troubleshooting firewall access for non-SUSE clients, see [[Administration › Tshoot-firewalls ›](#)].

Supported Client Systems

Supported operating systems for traditional and Salt clients are listed in this table.

In this table, ✓ indicates that clients running the operating system are supported by SUSE, and ✗ indicates that it is not supported. Fields marked as ? are under consideration, and may or may not be supported at a later date.



For SUSE operating systems, the version and SP level must be under general support (normal or LTSS) to be supported with SUSE Manager. For details on supported product versions, see <https://www.suse.com/lifecycle>. For non-SUSE operating systems, including Red Hat Enterprise Linux, CentOS, and Oracle Linux, only the latest available version is under general support.

Table 10. Supported Client Systems

Operating System	Architecture	Traditional Clients	Salt Clients
SUSE Linux Enterprise 15	x86_64, IBM Power PC, IBM Z, ARM	✓	✓
SUSE Linux Enterprise 12	x86_64, IBM Power PC, IBM Z, ARM	✓	✓
SUSE Linux Enterprise 11	x86, x86_64, {ppc64}, IBM Z	✓	✓
SUSE Linux Enterprise Server-ES 8	x86_64	✓	✓
SUSE Linux Enterprise Server-ES 7	x86_64	✓	✓
SUSE Linux Enterprise Server-ES 6	x86, x86_64	✓	✓
SUSE Linux Enterprise Server for SAP	x86_64, IBM Power PC	✓	✓

Operating System	Architecture	Traditional Clients	Salt Clients
Red Hat Enterprise Linux 8	x86_64	✗	✓
Red Hat Enterprise Linux 7	x86_64	✓	✓
Red Hat Enterprise Linux 6	x86, x86_64	✓	✓
CentOS 8	x86_64	✗	✓
CentOS 7	x86_64	✓	✓
CentOS 6	x86, x86_64	✓	✓
Oracle Linux 8	x86_64	✗	✓
Oracle Linux 7	x86_64	✓	✓
Oracle Linux 6	x86, x86_64	✓	✓
openSUSE Leap 15	x86_64	✗	✓
Ubuntu 20.04	x86_64	✗	✓
Ubuntu 18.04	x86_64	✗	✓
Ubuntu 16.04	x86_64	✗	✓

When you are setting up your client hardware, you need to ensure you have enough for the operating system and for the workload you want to perform on the client, with these additions for SUSE Manager:

Table 11. Client Additional Hardware Requirements

Hardware	Additional Size Required
RAM	512 MB
Disk Space:	200 MB

Public Cloud Requirements

You can run SUSE Manager Server on a public cloud instance from a third-party provider such as Amazon EC2, or Microsoft Azure.

This section details the requirements for using SUSE Manager on a public cloud instance.



Public clouds provide SUSE Manager under a Bring Your Own Subscription (BYOS) model. This means that you must have SUSE product entitlements to use SUSE Manager. For more information about public cloud entitlements, see [[Installation › Pubcloud-setup ›](#)].

Depending on the public cloud framework you are using, you can locate the SUSE Manager images by searching for the keywords `suse`, `manager`, `proxy`, or `BYOS`.

Instance Requirements

Select a public cloud instance type that meets the hardware requirements in [[Installation › Hardware-requirements ›](#)].

Before you begin, here are some other considerations:

- The SUSE Manager setup procedure performs a forward-confirmed reverse DNS lookup. This must succeed in order for the setup procedure to complete and for SUSE Manager to operate as expected. It is important to perform hostname and IP configuration before you set up SUSE Manager.
- SUSE Manager Server and Proxy instances need to run in a network configuration that provides you control over DNS entries, but cannot be accessed from the internet at large.
- Within this network configuration DNS resolution must be provided: `hostname -f` must return the fully qualified domain name (FQDN).
- DNS resolution is also important for connecting clients.
- DNS is dependent on the cloud framework you choose. Refer to the cloud provider documentation for detailed instructions.
- We recommend that you locate software repositories, the server database, and the proxy squid cache on an external virtual disk. This prevents data loss if the instance is unexpectedly terminated. This section includes instructions for setting up an external virtual disk.



If you are attempting to bootstrap traditional clients, check that you can resolve the host name of the server while you are logged in to the client. You might need to add the FQDN of the server to `/etc/hosts` local resolution file on the client. Check using the `hostname -f` command with the local IP address of the server.

Network Requirements

When you use SUSE Manager on a public cloud, you must use a restricted network. We recommend using a VPC private subnet with an appropriate firewall setting. Only machines in your specified IP ranges must be able to access the instance.



When you run SUSE Manager on public clouds, you must apply security measures to limit access to the instance. A world-accessible SUSE Manager instance violates the terms of the SUSE Manager EULA, and is not supported by SUSE.

To access the SUSE Manager Web UI, allow HTTPS when configuring the network access controls.

Separate Storage Volumes

We recommend that the repositories and the database for SUSE Manager are stored on separate storage devices to the root volume. This will help to avoid data loss. Do not use logical volume management (LVM) for public cloud installations.

You must set up the storage devices before you run the YaST SUSE Manager setup procedure.

Provision your disk devices in the public cloud environment, according the cloud provider's documentation. The size of the disk for repositories storage is dependent on the number of distributions and channels you intend to manage with SUSE Manager. When you attach the virtual disks, they will appear in your instance as Unix device nodes. The names of the device nodes will vary depending on your provider, and the instance type selected.

For more information about setting up storage volumes and partitions, including recommended minimum sizes, see [[Installation](#) › [Hardware-requirements](#) ›].

Installation

This section describes the process to install SUSE Manager components.

Installing SUSE Manager 4.1 Server

SUSE Manager is a SUSE product within the SUSE Linux Enterprise product family. This section describes how to install SUSE Manager Server from the SUSE Linux Enterprise installation media. For this topic we assume that you have already registered your SUSE Manager product with SUSE Customer Center and have obtained a registration code.

For information on registering with SUSE Customer Center, retrieving your organization credentials from SUSE Customer Center, or obtaining installation media, see [general-requirements.pdf](#).




To change a SUSE Linux Enterprise Server 15 SP2 into a SUSE Manager 4.1, follow the instructions at [[Installation](#) › [Install-vm](#) ›].




Before installing SUSE Manager, ensure your physical or virtual machine has enough disk space and RAM by checking the requirements at [Hardware](#).

Procedure: Installing SUSE Manager Server from a DVD Image


1. Boot your system with the Unified Installer. If booting fails you might need to adjust the boot order in the BIOS.
2. When prompted, select **Installation**.




3. In the **Language, Keyboard and Product Selection** screen, check the **SUSE Manager Server** checkbox, and click **[Next]**.
4. Read and agree to the End User Licence Agreement, and click **[Next]**.




5. In the **Registration** screen, check the **Register System via scc.suse.com** checkbox, enter your SUSE Customer Center credentials, and click **[Next]**.



6. In the **Extension and Module Selection** screen, select additional extensions or modules you require, and click **[Next]**. Mandatory modules are pre-selected and you cannot disable them.



7. OPTIONAL: In the **Add On Product** screen, select any additional or add-on products you require, and click **[Next]**. We do not recommend that you run any other workloads on SUSE Manager. Only use add-ons that you absolutely require, such as driver repositories from your hardware vendor.



8. In the **System Role** screen, check the **SUSE Manager Server** checkbox, and click **[Next]**.
9. In the **Suggested Partitioning** screen, either accept the default values, or use the **[Guided Setup]** or **[Expert Partitioner]** options to customize your partitioning model, and click **[Next]**.
10. In the **Clock and Time Zone** screen, enter your region and timezone, and click **[Next]**.
11. In the **Local Users** screen, create a new user, and click **[Next]**.
12. In the **System Administrator "root"** screen, create the "root" user, and click **[Next]**.
13. Review the settings on the **Installation Settings** screen.



Graphical Desktop Environment

The default SUSE Manager server installation does not enable a graphical desktop environment. If you want to run setup tools such as YaST with a graphical interface local on the SUSE Manager server, click **Software** and select the **X Window System** pattern.

On the **Installation Settings** screen click **[Install]**.

When the installation procedure has finished, you can check that you have all the required modules by using the `SUSEConnect --status-text` command at a command prompt. For SUSE Manager Server, the expected modules are:

- SUSE Linux Enterprise Server Basesystem Module
- Python 2 Module

- Server Applications Module
- Web and Scripting Module
- SUSE Manager Server Module

SUSE Manager 4.1 Proxy

SUSE Manager Proxy is a SUSE product within the SUSE Linux Enterprise product family. This section describes how to install SUSE Manager Proxy from SUSE Linux Enterprise installation media. It assumes you have already registered the SUSE Manager Proxy product with the SUSE Customer Center and have a registration code.

For information on registering with SUSE Customer Center, retrieving your organization credentials from SUSE Customer Center, or obtaining installation media, see [general-requirements.pdf](#).



If you want to install SUSE Manager Proxy on a virtual machine, ensure your virtual machine has enough disk space and RAM by checking the requirements at [hardware-requirements.pdf](#).

SUSE Manager Proxy is a SUSE Manager component that caches software packages on an internal server. The proxy also caches patch updates from SUSE or custom RPMs generated by third-party organizations. A proxy allows you to use bandwidth more effectively because client systems connect to the proxy for updates, and the SUSE Manager server is no longer required to handle all client requests. A SUSE Manager Proxy can serve both Traditional and Salt clients. The proxy also supports transparent custom package deployment.


SUSE Manager Proxy is an open source (GPLv2) solution that provides the following features:

- Cache software packages within a Squid proxy.
- Client systems see the SUSE Manager Proxy as a SUSE Manager server instance.
- The SUSE Manager Proxy is registered as a client system with the SUSE Manager server.

The primary goal of a SUSE Manager Proxy is to improve SUSE Manager performance by reducing bandwidth requirements and accelerating response time.

Procedure: Installing SUSE Manager Proxy with the Unified Installer

1. To boot the Unified Installer from the installation image, you might need to adjust the boot order in the BIOS.
2. When prompted, select **Installation**.
3. In the **Language, Keyboard and Product Selection** screen, check the **SUSE Manager Proxy** checkbox, and click **[Next]**.



4. Read and agree to the End User Licence Agreement, and click **[Next]**.
5. In the **Registration** screen, check the **Register System via scc.suse.com** checkbox, enter your SUSE Customer Center credentials, and click **[Next]**.
6. In the **Available Extensions and Modules** screen, select any extensions or modules you require, and click **[Next]**. **Basesystem**, **SUSE Manager Proxy**, and **Server Applications** are pre-selected and mandatory for a SUSE Manager Proxy installation. OPTIONAL: In the following **Add On Product** screen, select any additional or add-on products you require, and click **[Next]**.
7. In the **System Role** screen, check the **SUSE Manager Proxy** checkbox, and click **[Next]**.
8. In the **Suggested Partitioning** screen, accept the default values, or use the **[Guided Setup]** or **[Expert Practitioner]** options to customize your partitioning model, and click **[Next]**.
9. In the **Clock and Time Zone** screen, enter your region and timezone, and click **[Next]**.
10. In the **Local Users** screen, create a new user, and click **[Next]**.
11. Review the settings on the **Installation Settings** screen, and then click **[Install]**.

When the installation procedure has finished, you can check that you have all the required modules. At the command prompt, enter:

```
SUSEConnect --status-text
```

For SUSE Manager Proxy, the expected modules are:

- SUSE Linux Enterprise Server Basesystem Module
- Server Applications Module

- SUSE Manager Proxy Module

Continue with registering the installed SUSE Manager Proxy as a SUSE Manager client: [proxy-registration.pdf](#).

Install SUSE Manager in a Virtual Machine Environment with JeOS

Virtual Machine Manager (virt-manager) Settings

This chapter provides the required (KVM) settings for installation of SUSE Linux Enterprise Just Enough Operating System (JeOS) as the base for SUSE Manager. A kernel virtual machine (KVM) combined with Virtual Machine Manager (virt-manager) will be used as a sandbox for this installation.

Enter the following settings when creating a new virtual machine using **virt-manager**.



This table specifies the minimum requirements. These are suitable for a quick test installation, such as a server with one client. If you want to use a production environment, review the requirements listed in [hardware-requirements.pdf](#).

In the following table replace `version` with the actual product version string. Find the JeOS image at <https://download.suse.com/>.

KVM Settings	
Installation Method	Import Existing Disk Image
OS:	Linux
Version:	SLES_version_-JeOS-for-kvm-and-xen.x86_64-GM.qcow2
Memory:	8192 MB
CPU's:	4
Storage Format:	.qcow2 24 GB (Default) JeOS Root Partition
Virtual Disks:	
VirtIO Disk 2	101 GB for <code>/var/spacwalk</code>
VirtIO Disk 3	50 GB for <code>/var/lib/pgsql</code>
VirtIO Disk 4	4 GB for swap
Name:	test-setup

KVM Settings	
Network	Bridge br0



SUSE Linux Enterprise Virtualization Guide

For more information on virtualization, see <https://documentation.suse.com/sles/15-SP2/html/SLES-all/book-virt.html>.

JeOS KVM Settings

Create three additional virtual disks required for the SUSE Manager storage partitions.

Procedure: Creating the Required Partitions with KVM

1. Create a new virtual machine using the downloaded JeOS KVM image and select **Import existing disk image**.
2. Configure RAM and number of CPUs (at least 8 GB RAM and 4 CPUs).
3. Name your KVM machine and select the **Customize configuration before install** check box.
4. Click **[Add Hardware]** to create three new virtual disks with these specifications. These disks will be partitioned and mounted in [Procedure: Preparing JeOS for SUSE Manager Installation](#).



Storage size values are the absolute minimum—only suitable for a small test or demo installation. Especially **/var/pacewalk/** may quickly need more space. Also consider to create a separate partition for **/srv** where Kiwi images are stored.

VirtIO Storage Disks	Name	Sizing
VirtIO Disk 2	pacewalk	101 GB
VirtIO Disk 3	pgsql	50 GB
VirtIO Disk 4	swap	4 GB

5. Click **[Begin Installation]** to boot the new VM from the JeOS image.

Follow the prompts to complete the basic JeOS installation, until the process is complete and the command prompt waits for input.

During the basic installation prompts you are asked to enter the root password. In the next message box click **[Confirm root Password]**.

Preparing JeOS for SUSE Manager

Procedure: Preparing JeOS for SUSE Manager Installation

1. Log in as `root`.
2. Uninstall the `sles-release` package:

```
rpm -e --nodeps sles-release
```

3. Register SUSE Manager with SCC (for example, replace `<productnumber>` with `4.1` and `<architecture>` with `x86_64`):

```
SUSEConnect -e<EMAIL_ADDRESS> -r<SUSE_MANAGER_CODE> \  
-p SUSE-Manager-Server/<productnumber>/<architecture>
```

4. Add SUSE Manager repositories:

```
SUSEConnect -p sle-module-basesystem/15.2/x86_64  
SUSEConnect -p sle-module-python2/15.2/x86_64  
SUSEConnect -p sle-module-server-applications/15.2/x86_64  
SUSEConnect -p sle-module-web-scripting/15.2/x86_64  
SUSEConnect -p sle-module-suse-manager-server/<productnumber>/x86_64
```

JeOS is configured to install only required packages. To get all features working you should allow to install also recommended packages. In `/etc/zypp/zypp.conf` change:

```
solver.onlyRequires = true
```

To:

```
solver.onlyRequires = false
```

5. Install `yast2-storage-ng` with all required dependencies (approx. 40 packages, 30 MB when installed). This basic administration package is required for preparing storage partitions:

```
zypper in yast2-storage-ng
```

6. Partition and mount the virtual disks at the following locations using YaST Partitioner (`yast2 disk`).



Storage size values are the absolute minimum. They are suitable only for a small test or demonstration installation, such as a server with one client. Especially `/var/spacewalk/` may quickly need more space. Also consider to create a separate partition for `/srv` where Kiwi images are stored.

VirtIO Storage Disks	Name	Storage Size	File System Type
VirtIO Disk 2	<code>/var/spacewalk</code>	101 GB	XFS
VirtIO Disk 3	<code>/var/lib/pgsql</code>	50 GB	XFS
VirtIO Disk 4	<code>swap</code>	4 GB	swap

1. Exit the partitioner and install the SUSE Manager pattern (approximately 730 packages, using 1.4 GB of disk space when installed):

```
zypper in -t pattern suma_server
```

2. Reboot.

For proceeding with SUSE Manager setup, see [[Installation](#) › [Server-setup](#) › [SUSE Manager Setup](#)].

Install SUSE Manager Proxy from packages

To install SUSE Manager Proxy, you will need to start by installing SUSE Linux Enterprise Server media. This section covers the KVM settings required to perform a SUSE Linux Enterprise Server installation as the base for SUSE Manager Proxy. In this section, we use a KVM and a virtual machine manager as a sandbox for the installation.

SLES KVM Requirements

Use these settings to create a new virtual machine with `virt-manager` (replace `<version>` with the actual version string):

KVM Settings for SLES	Installation Method:
Local install media (ISO image or CDROM)	OS:
Linux	Version:
<code>SLE- <version> -Server-x86_64-GM-DVD1.iso</code>	Memory:
Test Server Minimum 2 GB	

KVM Settings for SLES	Installation Method:
Production Server Minimum 8 GB	CPUs:
2	Storage Format:
ISO 3 GB	Disk Space:
230 GB split between	
<code>/</code> (root) Minimum 24 GB	
(Virtual Disk 1) <code>/srv</code> Minimum 100 GB	
(Virtual Disk 2) <code>/var/cache</code> (Squid) Minimum 100 GB	Name:
example-proxy	Network

SLES KVM Settings

This section covers the SUSE Manager Proxy installation, using the full installation media with KVM and `virt-manager`. Before you begin, you will need to have created an account with SUSE Customer Center, and downloaded the SUSE Linux Enterprise Server installation media.

Procedure: Preparing for SLES Installation

1. In the Virtual Machine Manager tool (`virt-manager`), click **File > New Virtual Machine**.
2. Click **[Local install media (ISO image or CDROM)]**.
3. In the **Create a new virtual machine** dialog, click **[Browse]** and locate the full SLES image you downloaded from your SCC account.
4. Configure your machine with at least 2 GB RAM and a minimum of 2 CPUs.
5. Create a storage device with a minimum of 230 GB storage space for the installation. During the SLES installation this disk should be partitioned into the following partitions:

Disk Space Requirements
100 GB XFS partition (or dedicated virtual disk) for <code>/srv/</code>
100 GB XFS partition (or dedicated virtual disk) for <code>/var/cache/</code>

The remaining storage space will be used by the operating system for the root partition.

6. Click **[Finish]** to save the installation settings and begin the installation.

For more information on installing SUSE Linux Enterprise Server, see <https://documentation.suse.com/sles/15-SP2/html/SLES-all/art-sle-installquick.html>.

Change SLES for SUSE Manager Proxy

Procedure: Changing SLES for SUSE Manager Proxy Installation

1. Log in as `root`.
2. Uninstall the `sles-release` package:

```
rpm -e --nodeps sles-release
```

3. Register SUSE Manager Proxy with SCC (for example, replace `<productversion>` with `4.1` and `<architecture>` with `x86_64`):

```
SUSEConnect -e<EMAIL_ADDRESS> -r<SUSE_MANAGER_PROXY_CODE> \  
-p SUSE-Manager-Proxy/<productversion>/<architecture>
```

4. Add SUSE Manager repositories:

```
SUSEConnect -p sle-module-basesystem/15.2/x86_64  
SUSEConnect -p sle-module-server-applications/15.2/x86_64  
SUSEConnect -p sle-module-suse-manager-proxy/4.1/x86_64
```

5. Check that you have allowed installing recommended packages. Check the settings in `/etc/zypp/zypp.conf`:

```
solver.onlyRequires = false
```

6. Install the SUSE Manager Proxy pattern:

```
zypper in -t pattern suma_proxy
```

7. Reboot.

Continue with registering the installed SUSE Manager Proxy as a SUSE Manager client: [proxy-registration.pdf](#).

Installing on IBM Z

This section is intended for z/VM systems programmers responsible for operating the IBM Z mainframes. It assumes that you are a z/VM systems programmer trained on IBM Z operating protocols, and steps you through installing SUSE Manager onto an existing mainframe system. This section does not cover the variety of hardware configuration profiles available on IBM Z, but provides a foundational overview of the procedure and requirements necessary for a successful SUSE Manager Server deployment on IBM Z.

This section describes how to install SUSE Manager Server using SUSE Linux Enterprise installation media. You must have already registered your SUSE Manager product with SUSE Customer Center, and have obtained a registration code.

For information on registering with SUSE Customer Center, retrieving your organization credentials from SUSE Customer Center, or obtaining installation media, see [general-requirements.pdf](#).

System Requirements

Before you begin, check that your environment meets the base system requirements.

Compatible IBM Z Systems:

- IBM zEnterprise System z196
- IBM zEnterprise System z114
- IBM zEnterprise EC12
- IBM zEnterprise EC12
- IBM zEnterprise BC12
- IBM z13
- LinuxOne Rockhopper
- LinuxOne Emperor

Table 12. Hardware Requirements

Hardware	Recommended
CPU	Minimum 4 dedicated 64-bit CPU cores
RAM:	Test Server: Minimum 3 GB RAM and 2 GB Swap space
	Base Installation: Minimum 16 GB
	Production Server: Minimum 32 GB
Disk Space:	Root Partition: Minimum 100 GB
	<code>/var/lib/pgsql</code> : Minimum 50 GB
	<code>/var/spacwalk</code> : Minimum 50 GB per SUSE product and 360 GB per Red Hat product



Memory should be split across available RAM, VDISK, and swap to suit your environment. On a production system the ratio of physical memory to VDISK will need to be evaluated based on the number of clients you will be installing.

You will require an additional disk for database storage. This should be an **zFCP** or **DASD** device as these are preferred for use with **HYPERPAV**. The database storage disk should have:

- At least 50 GB for **/var/lib/pgsql**
- At least 50 GB for each SUSE product in **/var/pacewalk**
- At least 360 GB for each Red Hat product in **/var/pacewalk**

You will need to ensure you have sufficient disk storage for SUSE Manager before running **yast2 susemanager_setup**. By default, the SUSE Manager file system, including the embedded database and patch directories, reside within the root directory. While adjustments are possible when installation is complete, it is important that you specify and monitor these adjustments closely. For information on storage management and reclaiming disk space, see the troubleshooting section in the SUSE Manager Administration Guide.



If your SUSE Manager runs out of disk space, this can have a severe impact on its database and file structure. A full recovery is only possible with a previous backup or a new SUSE Manager installation. SUSE technical services will not be able to provide support for systems suffering from low disk space conditions.

Network Requirements:

- OSA Express Ethernet (including Fast and Gigabit Ethernet)
- HiperSockets or Guest LAN
- 10 GBE, VSWITCH
- RDMA over Converged Ethernet (RoCE)

These interfaces are still included but no longer supported:

- CTC or virtual CTC
- IP network interface for IUCV

The z/VM guest you want to run SUSE Manager from will require a static IP address and hostname before you begin, as these cannot easily be changed after initial installation. The hostname should contain less than eight characters and must not contain any upper case letters.

Media Requirements:

For media requirements, see [\[installation:general-requirements\]](#).

Install SUSE Manager on IBM Z

This section covers the installation of SUSE Manager as a product of the SUSE Linux Enterprise family. For general information about deploying a product on IBM Z hardware, see <https://documentation.suse.com/sles/15-SP2/html/SLES-all/cha-zseries.html>.

Procedure: Installing SUSE Manager Server from a DVD Image

1. Boot your system with the Unified Installer. If booting fails you might need to adjust the boot order in the BIOS.
2. When prompted, select **Installation**.

Then continue as described in [\[Installation › Install-server-unified › \]](#).

To finalize the SUSE Manager installation see [\[Installation › Server-setup › \]](#).

Setting Up

This section describes the initial steps you need to take after installation to make your SUSE Manager environment ready to use.

SUSE Manager Server Setup

This section covers SUSE Manager Server setup, using these procedures:

- Start SUSE Manager setup with YaST
- Create the main administration account with the SUSE Manager Web UI
- Name your base organization and add login credentials
- Synchronize the SUSE Linux Enterprise product channel from SUSE Customer Center



SUSE Manager is part of the SUSE Linux Enterprise product family and thus compatible with the software shipped with SUSE Linux Enterprise Server.

SUSE Manager is a complex system, and therefore installing third party software is not allowed. Installing monitoring software provided by a third party vendor is allowed only if you do not exchange basic libraries such as SSL, cryptographic software, and similar tools. As part of providing product support, SUSE reserves the right to ask to remove any third party software (and associated configuration changes) and then to reproduce the problem on a clean system.



Do not register a SUSE Manager Server to itself. The SUSE Manager Server must be managed individually or by using another separate SUSE Manager Server. For more information about using multiple servers, see [[Large-deployments > Multi-server >](#)].

Set up SUSE Manager with YaST

This section guides you through SUSE Manager setup using YaST.

Procedure: SUSE Manager Setup

1. On the SUSE Manager Server, at the command line, use the `yast2 susemanager_setup` command to begin setup.
2. From the introduction screen select **SUSE Manager Setup > Setup SUSE Manager from scratch** and click **[Next]** to continue.
3. Enter an email address to receive status notifications and click **[Next]** to continue. SUSE

Manager can sometimes send a large volume of notification emails. You can disable email notifications in the Web UI after setup, if you need to.

4. Enter your certificate information and a password. If you intend to use a custom SSL certificate, you need to have set this up first. For more information about SSL certificates, see [[Administration > Ssl-certs >](#)].
5. Click **[Next]** to continue.
6. From the **SUSE Manager Setup > Database Settings** screen, enter a database user and password and click **[Next]** to continue.
7. Click **[Next]** to continue.
8. Click **[Yes]** to run setup when prompted, and wait for it to complete.
9. Click **[Next]** to continue. Take a note of the address of the SUSE Manager Web UI.
10. Click **[Finish]** to complete SUSE Manager setup.



When you create your certificate password, ensure it is at least seven characters in length. It must not contain spaces, single or double quotation marks (' or "), exclamation marks (!), or dollar signs (\$). Always store your passwords in a secure location. Without this password it will not be possible to set up a SUSE Manager Proxy Server.

```

YaST2 - sussemanager_setup @ g137

Certificate Setup

Organization
Example
Organization Unit
Example Dep.
City
n
State
by
Country
DE
SSL Password
*****
Repeat Password
*****

[Help]          [Back]          [Abort]          [Next]

F1 Help  F8 Back  F9 Abort  F10 Next
  
```

```

YaST2 - susemanager_setup @ g137

Database Settings

Database User
susemanager

Database Password
*****

Repeat Password
*****

[Help]          [Back]          [Abort]        [Next]

F1 Help  F8 Back  F9 Abort  F10 Next

```

Creating the Main Administration Account

This section guides you through creating your organization's main administration account for SUSE Manager.



The main administration account is the highest authority account within SUSE Manager and therefore account access information should be stored in a secure location.

For security it is recommended that the main administrator creates low level admin accounts designated for administration of organizations and individual groups.

Procedure: Setting Up the Main Administration Account

1. In the browser, enter the address provided after completing setup. With this address you open the SUSE Manager Web UI.
2. In the Web UI, navigate to the **Create Organization** › **Organization Name** field and enter your organization name.
3. In the **Create Organization** › **Desired Login** and **Create Organization** › **Desired Password** fields, enter your username and password.
4. Fill in the Account Information fields including an email for system notifications.
5. Click **[Create Organization]** to finish creating your administration account.

Create Organization

Organization Details

Organization Name*:

Tip: Between 3 and 128 characters

Create SUSE Manager Administrator

Create the first SUSE Manager Administrator account. This account will have access to all resources on this SUSE Manager. This account will also be able to create new users and delegate permissions to them.

Desired Login*:

Tip: Between 5 and 64 characters

Desired Password*:

Confirm Password*:

Password Strength:

Email*:

First Name*:

Last Name*:

* - Required Field

Create Organization

You are now presented with the SUSE Manager Home › Overview page.

Synchronizing Products from SUSE Customer Center

SUSE Customer Center (SCC) maintains a collection of repositories which contain packages, software and updates for all supported enterprise client systems. These repositories are organized into channels each of which provide software specific to a distribution, release, and architecture. After synchronizing with SCC clients may receive updates, and be organized into groups and assigned to specific product software channels.

This section covers synchronizing with SCC from the Web UI and adding your first client channel.

Before you can synchronize software repositories with SCC, you will need to enter organization credentials in SUSE Manager. In previous versions, so-called mirror credentials were used instead. The organization credentials give you access to the SUSE product downloads. You will find your organization credentials in <https://scc.suse.com/organizations>.

Enter your organization credentials in the SUSE Manager Web UI:

Procedure: Entering Organization Credentials

1. In the SUSE Manager Web UI, select **Admin › Setup Wizard**.
2. From the **Setup Wizard** page select the **[Organization Credentials]** tab.
3. Click **[Add a new credential]**.
4. In the dialog, enter **Username** and **Password**, and confirm with **[Save]**.

When the credentials are confirmed with a check-mark icon, proceed with **Procedure:**

Synchronizing with SUSE Customer Center.

Procedure: Synchronizing with SUSE Customer Center

1. In the Web UI, navigate to **Admin › Setup Wizard**.
2. From the **Setup Wizard** page select the **[SUSE Products]** tab. Wait a moment for the products list to populate. If you previously registered with SUSE Customer Center a list of products will populate the table. This table lists architecture, channels, and status information. For more information, see [**Reference › Admin › Wizard**].

Setup Wizard

HTTP Proxy Organization Credentials **SUSE Products**

Filter by product Description Filter by architecture 25 items per page

Items 1 - 25 of 94

Product Description	Arch	Channels
<input type="checkbox"/> Open Enterprise Server 2018	x86_64	<input type="checkbox"/>
<input type="checkbox"/> RHEL Expanded Support 5	i386	<input type="checkbox"/>
<input type="checkbox"/> RHEL Expanded Support 5	x86_64	<input type="checkbox"/>
<input type="checkbox"/> > RHEL Expanded Support 6	i386	<input type="checkbox"/>
<input type="checkbox"/> > RHEL Expanded Support 6	x86_64	<input type="checkbox"/>
<input type="checkbox"/> > RHEL Expanded Support 7	x86_64	<input type="checkbox"/>
<input type="checkbox"/> SUSE Container as a Service Platform 1.0	x86_64	<input type="checkbox"/>
<input type="checkbox"/> SUSE Container as a Service Platform 2.0	x86_64	<input type="checkbox"/>
<input type="checkbox"/> > SUSE Linux Enterprise Desktop 11 SP2	i586	<input type="checkbox"/>
<input type="checkbox"/> > SUSE Linux Enterprise Desktop 11 SP2	x86_64	<input type="checkbox"/>
<input type="checkbox"/> > SUSE Linux Enterprise Desktop 11 SP3	i586	<input type="checkbox"/>
<input type="checkbox"/> > SUSE Linux Enterprise Desktop 11 SP3	x86_64	<input type="checkbox"/>
<input type="checkbox"/> > SUSE Linux Enterprise Desktop 11 SP4	i586	<input type="checkbox"/>
<input type="checkbox"/> > SUSE Linux Enterprise Desktop 11 SP4	x86_64	<input type="checkbox"/>
<input type="checkbox"/> > SUSE Linux Enterprise Desktop 12	x86_64	<input type="checkbox"/>
<input type="checkbox"/> > SUSE Linux Enterprise Desktop 12 SP1	x86_64	<input type="checkbox"/>
<input type="checkbox"/> > SUSE Linux Enterprise Desktop 12 SP2	x86_64	<input type="checkbox"/>
<input type="checkbox"/> > SUSE Linux Enterprise Desktop 12 SP3	x86_64	<input type="checkbox"/>
<input checked="" type="checkbox"/> > SUSE Linux Enterprise Desktop 15	x86_64	<input checked="" type="checkbox"/> 100% <input type="checkbox"/>
<input type="checkbox"/> > SUSE Linux Enterprise High Performance Computing 15	aarch64	<input checked="" type="checkbox"/> include recommended
<input type="checkbox"/> > SUSE Linux Enterprise High Performance Computing 15	x86_64	<input checked="" type="checkbox"/> include recommended
<input type="checkbox"/> > SUSE Linux Enterprise Server 10 SP3	i586	<input type="checkbox"/>
<input type="checkbox"/> > SUSE Linux Enterprise Server 10 SP3	ia64	<input type="checkbox"/>
<input type="checkbox"/> > SUSE Linux Enterprise Server 10 SP3	ppc	<input type="checkbox"/>
<input type="checkbox"/> > SUSE Linux Enterprise Server 10 SP3	s390x	<input type="checkbox"/>

Page 1 of 4 First Prev Next Last

← Prev 3 of 3

Refresh the product catalog from SUSE Customer Center

☐ Channels
☐ Channel Families
☐ Products
☐ Product Channels
☐ Subscriptions

Refresh

Why aren't all SUSE products displayed in the list?

The products displayed on this list are directly linked to your Organization credentials (Mirror credentials) as well as your SUSE subscriptions.

If you believe there are products missing, make sure you have added the correct Organization credentials in the previous wizard step.

3. If your SUSE Linux Enterprise client is based on **x86_64** architecture scroll down the page and select the check box for this channel now.

- Add channels to SUSE Manager by selecting the check box to the left of each channel. Click the arrow symbol to the left of the description to unfold a product and list available modules.
- Click **[Add Products]** to start product synchronization.

After adding the channel, SUSE Manager will schedule the channel to be synchronized. This can

take a long time as SUSE Manager will copy channel software sources from the SUSE repositories located at SUSE Customer Center to local `/var/pacewalk/` directory of your server.



PostgreSQL and Transparent Huge Pages

In some environments, Transparent Huge Pages provided by the kernel may slow down PostgreSQL workloads significantly.

To disable Transparent Huge Pages set the `transparent_hugepage` kernel parameter to `never`. This has to be changed in `/etc/default/grub` and added to the line `GRUB_CMDLINE_LINUX_DEFAULT`, for example:

```
GRUB_CMDLINE_LINUX_DEFAULT="resume=/dev/sda1 splash=silent
quiet showopts elevator=noop transparent_hugepage=never"
```

To write the new configuration run `grub2-mkconfig -o /boot/grub2/grub.cfg`.

Monitor the channel synchronization process in real-time by viewing channel log files located in the directory `/var/log/rhn/reposync`:

```
tail -f /var/log/rhn/reposync/<CHANNEL_NAME>.log
```

When the channel synchronization process is complete, you can continue with client registration. For more instructions, see [[Client-configuration](#) › [Registration-overview](#) ›].

SUSE Manager Proxy Registration

SUSE Manager Proxy systems are registered as Salt or traditional clients using a bootstrap script. Migrating a traditionally registered Proxy system to a Salt Proxy system is not possible. Re-install the Proxy if you want to switch to Salt.

This procedure describes software channel setup and registering the installed SUSE Manager Proxy with an activation key as a SUSE Manager client.





When choosing a username or password for your SUSE Manager Proxy, ensure it does not contain an `@` or `:` character. These characters are reserved.



Before you can select the correct child channels while creating the activation key, ensure you have completely downloaded the SUSE Manager Proxy 4.1 channel and all the recommended and mandatory SUSE Linux Enterprise 15 SP2 channels.

Procedure: Registering the Proxy

1. Create an activation key based on the **SLE-Product-SUSE-Manager-Proxy-4.1-Pool** base channel. For more information about activation keys, see [[Client-configuration > Activation-keys >](#)].

 **Create Activation Key** 

Activation Key Details

Systems registered with this activation key will inherit the settings listed below.

Description:

Use this to describe what kind of settings this key will reflect on systems that use it. If left blank, this field will be filled in 'None'.

Key:

1-

Activation key can contains only numbers [0-9], letters [a-z A-Z], '-', '_' and '.'

Leave blank for automatic key generation. Note that the prefix is an indication of the SUSE Manager organization the key is associated with.

Usage:

Leave blank for unlimited use.

Base Channel:

Choose "SUSE Manager Default" to allow systems to register to the default SUSE Manager provided channel that corresponds to the installed SUSE Linux version. Instead of the default, you may choose a particular SUSE provided channel or a custom base channel, but if a system using this key is not compatible with the selected channel, it will fall back to its SUSE Manager Default channel.

Child Channels:

✓ SLE-Product-SUSE-Manager-Proxy-4.0-Pool for x86_64

☒ Include recommended







- ☒ SLE-Module-Basesystem15-SP1-Pool for x86_64 Proxy 4.0  recommended 
- ☒ SLE-Module-Basesystem15-SP1-Updates for x86_64 Proxy 4.0  recommended 
- ☒ SLE-Module-Server-Applications15-SP1-Pool for x86_64 Proxy 4.0  recommended 

Figure 1. Proxy Activation Key

2. From the **Child Channels** listing select the recommended channels by clicking the **include recommended** icon:
 - SLE-Module-Basesystem15-SP2-Pool
 - SLE-Module-Basesystem15-SP2-Updates
 - SLE-Module-Server-Applications15-SP2-Pool
 - SLE-Module-Server-Applications15-SP2-Updates
 - SLE-Module-SUSE-Manager-Proxy-4.1-Pool

◦ SLE-Module-SUSE-Manager-Proxy-4.1-Updates

The **SLE-Product-SUSE-Manager-Proxy-4.1-Updates** channel is mandatory.

Base Channel:

SLE-Product-SUSE-Manager-Proxy-4.0-Pool for x86_64

Choose "SUSE Manager Default" to allow systems to register to the default SUSE Manager provided channel that corresponds to the installed SUSE Linux version. Instead of the default, you may choose a particular SUSE provided channel or a custom base channel, but if a system using this key is not compatible with the selected channel, it will fall back to its SUSE Manager Default channel.

Child Channels:

SLE-Product-SUSE-Manager-Proxy-4.0-Pool for x86_64

☒ Include recommended

☒ SLE-Module-Basesystem15-SP1-Pool for x86_64 Proxy 4.0 recommended

☒ SLE-Module-Basesystem15-SP1-Updates for x86_64 Proxy 4.0 recommended

☒ SLE-Module-Server-Applcations15-SP1-Pool for x86_64 Proxy 4.0 recommended

☒ SLE-Module-Server-Applcations15-SP1-Updates for x86_64 Proxy 4.0 recommended

☒ SLE-Module-SUSE-Manager-Proxy-4.0-Pool for x86_64 recommended

☒ SLE-Module-SUSE-Manager-Proxy-4.0-Updates for x86_64 recommended

☒ SLE-Product-SUSE-Manager-Proxy-4.0-Updates for x86_64 mandatory

Any system registered using this activation key will be subscribed to the selected child channels.

Add-On System Types:

☐ Container Build Host

☐ OS Image Build Host

☐ Virtualization Host

Contact Method:

Default

Universal Default:

☐

Figure 2. Base and Child Proxy Channel

3. Modify a bootstrap script for the proxy if needed. If you want to run the proxy on a traditional client (system type **Management**) uncheck **Bootstrap using Salt**. Using Salt is the default. For more information about bootstrap scripts, see [[Client-configuration > Registration-bootstrap >](#)].

SUSE Manager Configuration - Bootstrap

The following information will be used to generate bootstrap scripts. These bootstrap scripts can be used to configure a client to use SUSE Manager. Once the bootstrap scripts have been generated, they will be available from [this server](#).

Please note that some manual configuration of these scripts may still be required. The bootstrap script can be found on the SUSE Manager [server](#) at `/srv/www/htdocs/pub/bootstrap`.

General

Bootstrap Script

Organizations

Restart

Cobbler

Bare-metal systems

Client Bootstrap Script Configuration

SUSE Manager server hostname*

suma-refhead-srv.mgr.suse.de

SSL cert location*

/srv/www/htdocs/pub/rhn-org-trusted-ssl-cert-1.0-1.noarch.rpm

Bootstrap using Salt

☒

Enable SSL

☒

Enable Client GPG checking

☒

Enable Remote Configuration

☐

Enable Remote Commands

☒

Client HTTP Proxy

Client HTTP Proxy username

Client HTTP Proxy password

Update

Figure 3. Modifying Bootstrap Script

- Bootstrap the client with the bootstrap script.
- For Salt clients, accept the key on the **Salt > Keys** page by checking the appropriate checkbox. When accepted, it will appear in the **Systems > Overview**.
- Navigate to **System Details > Software > Software Channels**, and check that the four proxy channels (**Pool** and **Updates** for **SLE-PRODUCT** and **SLE-MODULE**) plus the recommended channels are selected. **SLE-PRODUCT-Pool** must be the base channel and the others are child channels.




Figure 4. Proxy Channels

Continue with setting up the registered SUSE Manager Proxy: [proxy-setup.pdf](#).

SUSE Manager Proxy Setup

SUSE Manager Proxy requires additional configuration.



Proxy Chains

It is possible to arrange Salt proxies in a chain. In such a case, the upstream proxy is named **parent**.

Make sure the TCP ports **4505** and **4506** are open on the proxy. The proxy must be able to reach the SUSE Manager Server or a parent proxy on these ports.

Copy Server Certificate and Key

The proxy will share some SSL information with the SUSE Manager Server. Copy the certificate and its key from the SUSE Manager Server or the parent proxy.

As root, enter the following commands on the proxy using your SUSE Manager Server or parent Proxy (named **PARENT**):

```
mkdir -m 700 /root/ssl-build
cd /root/ssl-build
scp root@PARENT:/root/ssl-build/RHN-ORG-PRIVATE-SSL-KEY .
scp root@PARENT:/root/ssl-build/RHN-ORG-TRUSTED-SSL-CERT .
scp root@PARENT:/root/ssl-build/rhn-ca-openssl.cnf .
```



To keep the security chain intact, the SUSE Manager Proxy functionality requires the SSL certificate to be signed by the same CA as the SUSE Manager Server certificate. Using certificates signed by different CAs for proxies and server is not supported.

Run `configure-proxy.sh`

The `configure-proxy.sh` script finalizes the setup of your SUSE Manager Proxy.

Execute the interactive `configure-proxy.sh` script. Pressing *Enter* without further input will make the script use the default values provided between brackets `[]`. Here is some information about the requested settings:

SUSE Manager Parent

A SUSE Manager parent can be either another proxy or a SUSE Manager Server.

HTTP Proxy

A HTTP proxy enables your SUSE Manager proxy to access the Web. This is needed if direct access to the Web is prohibited by a firewall.

Traceback Email

An email address where to report problems.

Use SSL

For safety reasons, press `Y`.

Do You Want to Import Existing Certificates?

Answer `N`. This ensures using the new certificates that were copied previously from the SUSE Manager server.

Organization

The next questions are about the characteristics to use for the SSL certificate of the proxy. The organization might be the same organization that was used on the server, unless of course your proxy is not in the same organization as your main server.

Organization Unit

The default value here is the proxy's hostname.

City

Further information attached to the proxy's certificate.

State

Further information attached to the proxy's certificate.

Country Code

In the `country code` field, enter the country code set during the SUSE Manager installation. For example, if your proxy is in the US and your SUSE Manager is in DE, enter `DE` for the proxy.



The country code must be two upper case letters. For a complete list of country codes, see <https://www.iso.org/obp/ui/#search>.

Cname Aliases (Separated by Space)

Use this if your proxy can be accessed through various DNS CNAME aliases. Otherwise it can be left empty.

CA Password

Enter the password that was used for the certificate of your SUSE Manager Server.

Do You Want to Use an Existing SSH Key for Proxying SSH-Push Salt Minion?

Use this option if you want to reuse a SSH key that was used for SSH-Push Salt clients on the server.

Create and Populate Configuration Channel `rhnp_proxy_config_1000010001`?

Accept default `Y`.

SUSE Manager Username

Use same user name and password as on the SUSE Manager server.

If parts are missing, such as CA key and public certificate, the script prints commands that you must execute to integrate the needed files. When the mandatory files are copied, run `configure-proxy.sh` again. If you receive an HTTP error during script execution, run the script again.

`configure-proxy.sh` activates services required by SUSE Manager Proxy, such as `squid`, `apache2`, `salt-broker`, and `jabberd`.

To check the status of the proxy system and its clients, click the proxy system's details page on the Web UI (**Systems** › **Proxy**, then the system name). **Connection** and **Proxy** subtabs display various status information.

Enable PXE Boot

Synchronize Profiles and System Information

To enable PXE boot through a proxy, additional software must be installed and configured on both the SUSE Manager Proxy and the SUSE Manager Server.

1. On the SUSE Manager Proxy, install the `susemanager-tftpsync-recv` package:

```
zypper in susemanager-tftpsync-recv
```

2. On the SUSE Manager Proxy, run the `configure-tftpsync.sh` setup script and enter the requested information:

```
configure-tftpsync.sh
```

You need to provide the hostname and IP address of the SUSE Manager Server and the proxy. You also need to enter the path to the tftpboot directory on the proxy.

3. On the SUSE Manager Server, install `susemanager-tftpsync`:

```
zypper in susemanager-tftpsync
```

1. On the SUSE Manager Server, run `configure-tftpsync.sh`. This creates the configuration, and uploads it to the SUSE Manager Proxy:

```
configure-tftpsync.sh FQDN_of_Proxy
```

2. Start an initial synchronization on the SUSE Manager Server:

```
cobbler sync
```

It can also be done after a change within Cobbler that needs to be synchronized immediately. Otherwise Cobbler synchronization will run automatically when needed. For more information about Cobbler, see [[Client-configuration](#) › [Cobbler](#) › [Cobbler](#)].

Configure DHCP for PXE through SUSE Manager Proxy

SUSE Manager uses Cobbler for client provisioning. PXE (tftp) is installed and activated by default. Clients must be able to find the PXE boot on the SUSE Manager Proxy using DHCP. Use this DHCP configuration for the zone that contains the clients to be provisioned:

```
next-server: <IP_Address_of_Proxy>
filename: "pxelinux.0"
```

Replace a SUSE Manager Proxy

A proxy does not contain any information about the clients that are connected to it. Therefore, a proxy can be replaced by a new one at any time. The replacement proxy must have the same name and IP address as its predecessor.

Shut down the old proxy, and leave it installed while you prepare the replacement. Create a reactivation key for this system and then register the new proxy using the reactivation key. If you do not use the reactivation key, you will need to re-register all the clients against the new proxy.



The reactivation key is only needed if you do not want to lose the history of the machine. If you do not use a reactivation key, the replacement proxy will become a "new" one with a new ID.

Procedure: Replacing a Proxy and Keeping the Clients Registered

1. Before starting the actual migration procedure, save the data from the old proxy, if needed. Consider copying important or manually created data to a central place that can also be accessed by the new proxy.
2. Shut down the proxy.
3. Install a new SUSE Manager Proxy. For installation instructions, see [Proxy Installation](#).
4. In the SUSE Manager Web UI, select the newly installed SUSE Manager Proxy, and delete it from the systems list.
5. In the Web UI, create a reactivation key for the old proxy system: On the System Details tab of the old proxy click **Reactivation**. Click **Generate New Key**, and make a note of the new key. For more information about reactivation keys, see [[Reference](#) › [Systems](#) › [Reactivation Keys](#)].
6. Register the proxy with a bootstrap script as described in [[Installation](#) › [Proxy-registration](#) ›]. In the bootstrap script set the reactivation key as **ACTIVATION_KEYS**.
7. Re-run the `configure-proxy.sh` as described in [installation:uyuni-proxy-setup.pdf](#).
8. OPTIONAL: After the installation of the new proxy, you might also need to:
 - Copy the centrally saved data to the new proxy system
 - Install any other needed software
 - Set up TFTP synchronization if the proxy is used for autoinstallation



During the installation of the proxy, clients will not be able to reach the SUSE Manager Server. After you have deleted a proxy, the systems list can be temporarily incorrect. All clients that were previously connected to the proxy will show as being directly connected to the server instead. After the first successful operation on a client, such as execution of a remote command or installation of a package or patch, this information will automatically be corrected. This may take some hours.

Web Interface Setup

To use the SUSE Manager Web UI, navigate to your SUSE Manager URL in a browser. Sign in to the Web UI using your SUSE Manager Administration account.

While you are using the Web UI, click the  icon to access the documentation for that section.

The first time you sign in to the Web UI, complete the setup wizard to set your user preferences. You can access the setup wizard at any time by navigating to **Admin › Setup Wizard**.

After the initial setup is complete, signing in will take you the **Home › Overview** section. This section contains summary panes that provide important information about your systems.

The **Tasks** pane provides shortcuts to the most common Web UI tasks.

The **Inactive Systems** pane shows any clients that have stopped checking in to the SUSE Manager Server. You will need to check these clients.

The **Most Critical Systems** pane shows any clients that require software updates. Click the name of a client in the list to be taken to the **Systems › System Details** section for that client. From this page, you can apply any required updates.


The **Recently Scheduled Actions** pane shows all recent actions that have been run, and their status. Click the label of an action to see more detail.

The **Relevant Security Patches** pane shows all available security patches that need to be applied to your clients. It is critical that you apply security patches as soon as possible to keep your clients secure.

The **System Groups** pane shows any system groups you have created, and if the clients in those groups are fully updated.

The **Recently Registered Systems** pane shows all clients registered in the past thirty days. Click the name of a client in the list to be taken to the **Systems › System Details** section for that client.

Web Interface Navigation

The SUSE Manager Web UI uses some standard elements to help you navigate. While you are using the Web UI, click the  icon to access the documentation for that section.

Top Navigation Bar

The top navigation bar gives access to system-wide functions.



Notifications

The notification bell icon displays the number of unread notification messages in a circle. Click the notification icon to go to [Home](#) › [Notification Messages](#).

Overview Legend

Click the eye icon to see commonly used icons for the currently active section of the Web UI.

Search

Click the search magnifying glass icon to open the search box. You can search for systems (clients), packages, patches, or documentation. Click  to go to the relevant  page, and see your search results.

Systems Selected

The systems selected icon displays the number of currently selected systems in a circle. Click the systems selected icon to go to [Systems](#) › [System Set Manager](#) › [Overview](#). Click the eraser icon to unselect all systems. For more information about the system set manager, see [\[Client-configuration › System-set-manager › \]](#).

User Account

The user account icon is displayed with the name of the currently signed-in user. Click the user account icon to go to [Home](#) › [User Account](#) › [My Account](#).

Organization

The organization icon is displayed with the name of the currently active organization. Click the organization icon to go to [Home](#) › [My Organization](#) › [Configuration](#).

Preferences

Click the cogs icon to go to [Home](#) › [My Preferences](#).

Sign Out

Click the exit icon to sign out the current user and return to the sign in screen.



If you add a distribution, newly synchronize channels, or register a system with a SUSE Manager server, it can take several minutes for it to be indexed and appear in search results. If you need to force a rebuild of the search index, use this command at the command prompt:

```
rhncleanindex
```

Left Navigation Bar

The left navigation bar is the main menu to the SUSE Manager Web UI.

Expand

If you click the icon or the down-arrow of a menu entry, it expands this part of the menu tree without actually loading a page.

Collapse

To collapse an open part of the menu system, click the up-arrow of a menu entry.

Autoload

If you click the name of a menu entry, the first available page of that menu entry will get loaded and displayed automatically.

Search

Enter a search string in the **Search page** field to find an entry of the menu tree. Available menu entries depend on the roles of the user.



Only SUSE Manager Administrators can access these sections:

- Images
- Users
- Admin


Tables


Many sections present information in tables. You can navigate through most tables by clicking the back and next arrows above and below the right side of the table. Change the default number of items shown on each page by navigating to **Home › My Preferences**.

You can filter the content in most tables using the search bar at the top of the table. Sort table entries by clicking on the column header you want to sort by. Click the column header again to reverse the sort.

Patch Alert Icons

Patches are represented by three main icons, depending on the type of patch. Icons are coloured either green, yellow, or red, depending on the severity.

 The shield icon is a security alert. A red shield is the highest priority security alert.

 The bug icon is a bug fix alert.

• The squares icon is an enhancement alert.

Some additional icons are used to give extra information:

 The circling arrows icon indicates that applying a patch will require a reboot.

 The archive box icon indicates that a patch will have an effect on package management.

Interface Customization

By default, the SUSE Manager Web UI uses the theme appropriate to the product you have installed. You can change the theme to reflect the Uyuni or SUSE Manager colors. The SUSE Manager theme also has a dark option available. To change the theme using the Web UI, navigate to **Home > My Preferences** and locate the **Style Theme** section.

For information about changing the default theme, see [**Administration > Users >**].

Public Cloud Setup

Public Cloud providers pre-install SUSE Manager, so you do not need to perform any installation steps. However, you must have the correct SUSE Manager and SUSE Linux Enterprise entitlements to receive updates before you can log in.

For most bring your own service (BYOS) images, these entitlements are provided by SUSE, and can be obtained using the SUSE Customer Center. If you are using an on demand image, you need to do some extra preparation before you can register to SUSE Customer Center.

When you have registered, all SUSE Linux Enterprise modules are activated. You can then activate the public cloud module.

Procedure: Preparing On Demand Images

1. Log in the on demand instance.
2. At the command prompt, as root, remove the **cloud-regionsrv-client** package:

```
zypper rm cloud-regionsrv-client
```

3. Remove additional packages specific to your cloud provider:

- Amazon EC2:

```
zypper rm regionServiceClientConfigEC2 regionServiceCertsEC2
```

- Google Compute Engine:

```
zypper rm cloud-regionsrv-client-plugin-gce regionServiceClientConfigGCE  
regionServiceCertsGCE
```

- Microsoft Azure:

```
zypper rm regionServiceClientConfigAzure regionServiceCertsAzure
```

4. Open the `/etc/hosts` file, and delete the entry that contains `@susecloud.net`.

5. Remove the `SUSEConnect` configuration file:

```
rm /etc/SUSEConnect
```

For instructions on registering SUSE Manager to SUSE Customer Center, see [[Installation > Server-setup >](#)].

Procedure: Activating the Public Cloud Module

1. On the SUSE Manager Server, open the YaST management tool, and navigate to **Software > Software Repositories**.
2. Click **[Add]** and select **Extensions and Modules from Registration Server**.
3. In the **Available extensions** field, select **Public Cloud Module**.

If you prefer to use the command line, you can add the module with this command:

```
SUSEConnect -p sle-module-public-cloud/15.2/x86_64
```

When the installation procedure has finished, you can check that you have all the required modules. At the command prompt, enter:

```
SUSEConnect --status-text
```

For SUSE Manager Server on a public cloud, the expected modules are:

- SUSE Linux Enterprise Server Basesystem Module
- Python 2 Module
- Server Applications Module
- Web and Scripting Module
- SUSE Manager Server Module
- Public Cloud Module

Account Credentials

An administrator account is created by default. The username and password varies depending on your provider.

Table 13. Default Administrator Account Details

Provider	Default Username	Default Password
Amazon EC2	admin	<instance-ID>
Google Compute Engine	admin	<instance-ID>
Microsoft Azure	admin	<instance-name> -suma

You can retrieve the instance name or ID from the public cloud instance web console, or from the command prompt:

Amazon EC2:

```
ec2metadata --instance-id
```

Google Compute Engine:

```
gcemetadata --query instance --id
```

Microsoft Azure:

```
azuremetadata --compute --name
```



When you have logged in to the administrator account for the first time, change the default password to protect your account.

Setup Wizard

When you have completed your SUSE Manager installation, you can use the setup wizard to complete the last few steps. The setup wizard allows you to configure the HTTP proxy, organization credentials, and SUSE products.

The setup wizard is displayed by default when you log in the SUSE Manager Web UI for the first time. You can access the setup wizard directly by navigating to **Admin** › **Setup Wizard**.

Configure the HTTP Proxy

SUSE Manager can connect to the SUSE Customer Center (SCC) or other remote servers using a proxy. Navigate to the **HTTP Proxy** tab to configure the proxy.

You will need to provide the hostname of the proxy. Use the syntax `<hostname>:<port>`. For example: `<example.com>:8080`.

You can disable use of the proxy by clearing the fields.



When choosing a username or password for your SUSE Manager Proxy, ensure it does not contain an `@` or `:` character. These characters are reserved.

Configure Organization Credentials

Your SUSE Customer Center account is associated with the administration account of your organization. You can share your SUSE Customer Center access with other users within your organization. Navigate to the **Organization Credentials** tab to grant users within your organization access to your SUSE Customer Center account.

Click **[Add a new credential]** enter the username and password of the user to grant access to, and click **[Save]**. A new credential card is shown for the user you have granted access to. Use these buttons on the card to edit or revoke access:

- Check credential validation status (green tick or red cross icon). To re-check the credential with SCC, click the icon.
- Set the primary credentials for inter-server synchronization (yellow star icon).
- List the subscriptions related to a certain credential (list icon).
- Edit the credential (pencil icon).
- Delete the credential (trash can icon).

Configure Products

Your SUSE subscription entitles you to access a range of products. Navigate to the **Products** tab to browse the products available to you and synchronize SUSE Manager with SUSE Customer Center.

Filters help you search for products by description or architecture.

The list is organized by product name. For each product, you can see the architecture it can be used on. Click the arrow next to the product name to see associated channels and extensions. Click the **[Channels]** icon to see the complete list of channels associated with each product.

For products based on SUSE Linux Enterprise 15 and above, you can choose to only synchronize required packages, or to also include recommended products. Toggle the **[include recommended]** switch on to synchronize all products, and toggle the switch off to synchronize only required products.

You can further refine which products you want to synchronize by selecting or deselecting individual product.

When you have completed your selection, click **[Add products]** and click **[Refresh]** to schedule the synchronization.

Synchronization progress for each product is shown in a progress bar next to the product name. Depending on the products you have chosen, synchronization can take up to several hours. New products will be available for you to use in SUSE Manager when synchronization is complete.

If your synchronization fails, it could be because of a third party GPG key. For more information about troubleshooting product synchronization, see [\[Administration › Tshoot-sync › \]](#).

GNU Free Documentation License

Copyright © 2000, 2001, 2002 Free Software Foundation, Inc. 51 Franklin St, Fifth Floor, Boston, MA 02110-1301 USA. Everyone is permitted to copy and distribute verbatim copies of this license document, but changing it is not allowed.

0. PREAMBLE

The purpose of this License is to make a manual, textbook, or other functional and useful document "free" in the sense of freedom: to assure everyone the effective freedom to copy and redistribute it, with or without modifying it, either commercially or noncommercially. Secondly, this License preserves for the author and publisher a way to get credit for their work, while not being considered responsible for modifications made by others.

This License is a kind of "copyleft", which means that derivative works of the document must themselves be free in the same sense. It complements the GNU General Public License, which is a copyleft license designed for free software.

We have designed this License in order to use it for manuals for free software, because free software needs free documentation: a free program should come with manuals providing the same freedoms that the software does. But this License is not limited to software manuals; it can be used for any textual work, regardless of subject matter or whether it is published as a printed book. We recommend this License principally for works whose purpose is instruction or reference.

1. APPLICABILITY AND DEFINITIONS

This License applies to any manual or other work, in any medium, that contains a notice placed by the copyright holder saying it can be distributed under the terms of this License. Such a notice grants a world-wide, royalty-free license, unlimited in duration, to use that work under the conditions stated herein. The "Document", below, refers to any such manual or work. Any member of the public is a licensee, and is addressed as "you". You accept the license if you copy, modify or distribute the work in a way requiring permission under copyright law.

A "Modified Version" of the Document means any work containing the Document or a portion of it, either copied verbatim, or with modifications and/or translated into another language.

A "Secondary Section" is a named appendix or a front-matter section of the Document that deals exclusively with the relationship of the publishers or authors of the Document to the Document's overall subject (or to related matters) and contains nothing that could fall directly within that overall subject. (Thus, if the Document is in part a textbook of mathematics, a Secondary Section may not explain any mathematics.) The relationship could be a matter of historical connection with the subject or with related matters, or of legal, commercial, philosophical, ethical or political position regarding them.

The "Invariant Sections" are certain Secondary Sections whose titles are designated, as being those of Invariant Sections, in the notice that says that the Document is released under this License. If a section does not fit the above definition of Secondary then it is not allowed to be designated as Invariant. The Document may contain zero Invariant Sections. If the Document does not identify any Invariant Sections then there are none.

The "Cover Texts" are certain short passages of text that are listed, as Front-Cover Texts or Back-Cover Texts, in the notice that says that the Document is released under this License. A Front-Cover Text may be at most 5 words, and a Back-Cover Text may be at most 25 words.

A "Transparent" copy of the Document means a machine-readable copy, represented in a format whose specification is available to the general public, that is suitable for revising the document straightforwardly with generic text editors or (for images composed of pixels) generic paint programs or (for drawings) some widely available drawing editor, and that is suitable for input to text formatters or for automatic translation to a variety of formats suitable for input to text formatters. A copy made in an otherwise Transparent file format whose markup, or absence of markup, has been arranged to thwart or discourage subsequent modification by readers is not Transparent. An image format is not Transparent if used for any substantial amount of text. A copy that is not "Transparent" is called "Opaque".

Examples of suitable formats for Transparent copies include plain ASCII without markup, Texinfo input format, LaTeX input format, SGML or XML using a publicly available DTD, and standard-conforming simple HTML, PostScript or PDF designed for human modification. Examples of transparent image formats include PNG, XCF and JPG. Opaque formats include proprietary formats that can be read and edited only by proprietary word processors, SGML or XML for which the DTD and/or processing tools are not generally available, and the machine-generated HTML, PostScript or PDF produced by some word processors for output purposes only.

The "Title Page" means, for a printed book, the title page itself, plus such following pages as are needed to hold, legibly, the material this License requires to appear in the title page. For works in formats which do not have any title page as such, "Title Page" means the text near the most prominent appearance of the work's title, preceding the beginning of the body of the text.

A section "Entitled XYZ" means a named subunit of the Document whose title either is precisely XYZ or contains XYZ in parentheses following text that translates XYZ in another language. (Here XYZ stands for a specific section name mentioned below, such as "Acknowledgements", "Dedications", "Endorsements", or "History".) To "Preserve the Title" of such a section when you modify the Document means that it remains a section "Entitled XYZ" according to this definition.

The Document may include Warranty Disclaimers next to the notice which states that this License applies to the Document. These Warranty Disclaimers are considered to be included by reference in this License, but only as regards disclaiming warranties: any other implication that these Warranty Disclaimers may have is void and has no effect on the meaning of this License.

2. VERBATIM COPYING

You may copy and distribute the Document in any medium, either commercially or noncommercially, provided that this License, the copyright notices, and the license notice saying this License applies to the Document are reproduced in all copies, and that you add no other conditions whatsoever to those of this License. You may not use technical measures to obstruct or control the reading or further copying of the copies you make or distribute. However, you may accept compensation in exchange for copies. If you distribute a large enough number of copies you must also follow the conditions in section 3.

You may also lend copies, under the same conditions stated above, and you may publicly display copies.

3. COPYING IN QUANTITY

If you publish printed copies (or copies in media that commonly have printed covers) of the Document, numbering more than 100, and the Document's license notice requires Cover Texts, you must enclose the copies in covers that carry, clearly and legibly, all these Cover Texts: Front-Cover Texts on the front cover, and Back-Cover Texts on the back cover. Both covers must also clearly and legibly identify you as the publisher of these copies. The front cover must present the full title with all words of the title equally prominent and visible. You may add other material on the covers in addition. Copying with changes limited to the covers, as long as they preserve the title of the Document and satisfy these conditions, can be treated as verbatim copying in other respects.

If the required texts for either cover are too voluminous to fit legibly, you should put the first ones listed (as many as fit reasonably) on the actual cover, and continue the rest onto adjacent pages.

If you publish or distribute Opaque copies of the Document numbering more than 100, you must either include a machine-readable Transparent copy along with each Opaque copy, or state in or with each Opaque copy a computer-network location from which the general network-using public has access to download using public-standard network protocols a complete Transparent copy of the Document, free of added material. If you use the latter option, you must take reasonably prudent steps, when you begin distribution of Opaque copies in quantity, to ensure that this Transparent copy will remain thus accessible at the stated location until at least one year after the last time you distribute an Opaque copy (directly or through your agents or retailers) of that edition to the public.

It is requested, but not required, that you contact the authors of the Document well before redistributing any large number of copies, to give them a chance to provide you with an updated version of the Document.

4. MODIFICATIONS

You may copy and distribute a Modified Version of the Document under the conditions of sections 2 and 3 above, provided that you release the Modified Version under precisely this License, with the Modified Version filling the role of the Document, thus licensing distribution and

modification of the Modified Version to whoever possesses a copy of it. In addition, you must do these things in the Modified Version:

- A. Use in the Title Page (and on the covers, if any) a title distinct from that of the Document, and from those of previous versions (which should, if there were any, be listed in the History section of the Document). You may use the same title as a previous version if the original publisher of that version gives permission.
- B. List on the Title Page, as authors, one or more persons or entities responsible for authorship of the modifications in the Modified Version, together with at least five of the principal authors of the Document (all of its principal authors, if it has fewer than five), unless they release you from this requirement.
- C. State on the Title page the name of the publisher of the Modified Version, as the publisher.
- D. Preserve all the copyright notices of the Document.
- E. Add an appropriate copyright notice for your modifications adjacent to the other copyright notices.
- F. Include, immediately after the copyright notices, a license notice giving the public permission to use the Modified Version under the terms of this License, in the form shown in the Addendum below.
- G. Preserve in that license notice the full lists of Invariant Sections and required Cover Texts given in the Document's license notice.
- H. Include an unaltered copy of this License.
- I. Preserve the section Entitled "History", Preserve its Title, and add to it an item stating at least the title, year, new authors, and publisher of the Modified Version as given on the Title Page. If there is no section Entitled "History" in the Document, create one stating the title, year, authors, and publisher of the Document as given on its Title Page, then add an item describing the Modified Version as stated in the previous sentence.
- J. Preserve the network location, if any, given in the Document for public access to a Transparent copy of the Document, and likewise the network locations given in the Document for previous versions it was based on. These may be placed in the "History" section. You may omit a network location for a work that was published at least four years before the Document itself, or if the original publisher of the version it refers to gives permission.
- K. For any section Entitled "Acknowledgements" or "Dedications", Preserve the Title of the section, and preserve in the section all the substance and tone of each of the contributor acknowledgements and/or dedications given therein.
- L. Preserve all the Invariant Sections of the Document, unaltered in their text and in their titles. Section numbers or the equivalent are not considered part of the section titles.
- M. Delete any section Entitled "Endorsements". Such a section may not be included in the Modified Version.
- N. Do not retitle any existing section to be Entitled "Endorsements" or to conflict in title with

any Invariant Section.

O. Preserve any Warranty Disclaimers.

If the Modified Version includes new front-matter sections or appendices that qualify as Secondary Sections and contain no material copied from the Document, you may at your option designate some or all of these sections as invariant. To do this, add their titles to the list of Invariant Sections in the Modified Version's license notice. These titles must be distinct from any other section titles.

You may add a section Entitled "Endorsements", provided it contains nothing but endorsements of your Modified Version by various parties—for example, statements of peer review or that the text has been approved by an organization as the authoritative definition of a standard.

You may add a passage of up to five words as a Front-Cover Text, and a passage of up to 25 words as a Back-Cover Text, to the end of the list of Cover Texts in the Modified Version. Only one passage of Front-Cover Text and one of Back-Cover Text may be added by (or through arrangements made by) any one entity. If the Document already includes a cover text for the same cover, previously added by you or by arrangement made by the same entity you are acting on behalf of, you may not add another; but you may replace the old one, on explicit permission from the previous publisher that added the old one.

The author(s) and publisher(s) of the Document do not by this License give permission to use their names for publicity for or to assert or imply endorsement of any Modified Version.

5. COMBINING DOCUMENTS

You may combine the Document with other documents released under this License, under the terms defined in section 4 above for modified versions, provided that you include in the combination all of the Invariant Sections of all of the original documents, unmodified, and list them all as Invariant Sections of your combined work in its license notice, and that you preserve all their Warranty Disclaimers.

The combined work need only contain one copy of this License, and multiple identical Invariant Sections may be replaced with a single copy. If there are multiple Invariant Sections with the same name but different contents, make the title of each such section unique by adding at the end of it, in parentheses, the name of the original author or publisher of that section if known, or else a unique number. Make the same adjustment to the section titles in the list of Invariant Sections in the license notice of the combined work.

In the combination, you must combine any sections Entitled "History" in the various original documents, forming one section Entitled "History"; likewise combine any sections Entitled "Acknowledgements", and any sections Entitled "Dedications". You must delete all sections Entitled "Endorsements".

6. COLLECTIONS OF DOCUMENTS

You may make a collection consisting of the Document and other documents released under this License, and replace the individual copies of this License in the various documents with a single copy that is included in the collection, provided that you follow the rules of this License for verbatim copying of each of the documents in all other respects.

You may extract a single document from such a collection, and distribute it individually under this License, provided you insert a copy of this License into the extracted document, and follow this License in all other respects regarding verbatim copying of that document.

7. AGGREGATION WITH INDEPENDENT WORKS

A compilation of the Document or its derivatives with other separate and independent documents or works, in or on a volume of a storage or distribution medium, is called an "aggregate" if the copyright resulting from the compilation is not used to limit the legal rights of the compilation's users beyond what the individual works permit. When the Document is included in an aggregate, this License does not apply to the other works in the aggregate which are not themselves derivative works of the Document.

If the Cover Text requirement of section 3 is applicable to these copies of the Document, then if the Document is less than one half of the entire aggregate, the Document's Cover Texts may be placed on covers that bracket the Document within the aggregate, or the electronic equivalent of covers if the Document is in electronic form. Otherwise they must appear on printed covers that bracket the whole aggregate.

8. TRANSLATION

Translation is considered a kind of modification, so you may distribute translations of the Document under the terms of section 4. Replacing Invariant Sections with translations requires special permission from their copyright holders, but you may include translations of some or all Invariant Sections in addition to the original versions of these Invariant Sections. You may include a translation of this License, and all the license notices in the Document, and any Warranty Disclaimers, provided that you also include the original English version of this License and the original versions of those notices and disclaimers. In case of a disagreement between the translation and the original version of this License or a notice or disclaimer, the original version will prevail.

If a section in the Document is Entitled "Acknowledgements", "Dedications", or "History", the requirement (section 4) to Preserve its Title (section 1) will typically require changing the actual title.

9. TERMINATION

You may not copy, modify, sublicense, or distribute the Document except as expressly provided for under this License. Any other attempt to copy, modify, sublicense or distribute the Document is void, and will automatically terminate your rights under this License. However, parties who

have received copies, or rights, from you under this License will not have their licenses terminated so long as such parties remain in full compliance.

10. FUTURE REVISIONS OF THIS LICENSE

The Free Software Foundation may publish new, revised versions of the GNU Free Documentation License from time to time. Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns. See <http://www.gnu.org/copyleft/>.

Each version of the License is given a distinguishing version number. If the Document specifies that a particular numbered version of this License "or any later version" applies to it, you have the option of following the terms and conditions either of that specified version or of any later version that has been published (not as a draft) by the Free Software Foundation. If the Document does not specify a version number of this License, you may choose any version ever published (not as a draft) by the Free Software Foundation.

ADDENDUM: How to use this License for your documents

Copyright (c) YEAR YOUR NAME.

Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.2 or any later version published by the Free Software Foundation; with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts. A copy of the license is included in the section entitled "GNU Free Documentation License".

If you have Invariant Sections, Front-Cover Texts and Back-Cover Texts, replace the "with... Texts." line with this:

with the Invariant Sections being LIST THEIR TITLES, with the Front-Cover Texts being LIST, and with the Back-Cover Texts being LIST.

If you have Invariant Sections without Cover Texts, or some other combination of the three, merge those two alternatives to suit the situation.

If your document contains nontrivial examples of program code, we recommend releasing these examples in parallel under your choice of free software license, such as the GNU General Public License, to permit their use in free software.